



Software Installation Guide

Version 1.6.0

Contents

Copyright Notice	3
Document Revision History	4
Client Skin Pack Addition	5
Preparation	5
Backup	5
Installer	6
Web Interface	10
Preparation	10
Installer	11

Copyright Notice

No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without express written permission. Under the law, reproducing includes translating into another language or format.

The software is protected by United States copyright laws and international treaty provision. Therefore, you must treat the software like any other copyrighted material (e.g. a book or sound recording).

Document Revision History

February 11th, 2017

- Initial release of documentation.

Client Skin Pack Addition

Preparation


To set install the Beam Client Skin Pack Addition, you must have:

- Access to the Qumu Video Control Center application server
- Ability to update the current skin pack

Backup


The installer creates a new version of the Qumu skin pack file located at **/js/dojo18/mpi/layers/vp_program.js**. It is unlikely that your custom skin pack also modifies this file, however it is recommended that you backup your skin pack directory prior to installation. The directory is typically located at:

```
C:\Program Files\Qumu\tomcat\base\webapps\viewerportal\WEB-INF\skinresources\custom
```




Installer


1. Copy the installer file (named **beam-client-installer.v.1.5.6.exe** or similar) to the desktop of the VCC application server.



2. Double-click on the installer file, locate the Qumu VCC directory, enter the Qumu Viewer portal domain, and the Beam Cluster hostname, then click **Install**.




3. Click **OK** to confirm the information dialog.



4. Navigate to the skin tools form and create a new skin pack. If the Viewer Portal hostname were **qumu.example.com** and the domain were **tube**, the skin tools URL would be:

`https://qumu.example.com/viewerportal/tube/skintools.vp`



5. Remove the installer file from the Desktop.

Web Interface

Preparation

To set install the Beam Web Interface, you must have:

- Access to the Qumu Video Control Center web server
- Ability to update Microsoft IIS settings


System Requirements

Supported Platforms


- Qumu VCC 7.5 and later
- Microsoft IIS 7.5 and later

Installer


1. Copy the installer file (named **beam-web-installer.v1.5.6.exe** or similar) to the desktop of the VCC web server.




2. Double-click on the installer file, enter the Beam Cluster hostname, then click **Install**.



3. Click **Close** when the installation is complete.



- To confirm the installation, open **IIS Manager** and look for the **/adminportal/beam** virtual directory in the **Default Web Site**.



- Remove the installer file from the Desktop.